


DYNAmore Express Webinar on 6 May 2022

# Beyond FEA: Arbitrary-Lagrangian-Eulerian (ALE) Method

Maik Schenke, DYNAmore GmbH



Courtesy of DLR

© 2022 DYNAmore GmbH

Slide 1 of 33

# Introduction

---


First things first

# Introduction

## LS-DYNA Multi-Physic Solver

- One Code for all

- Structural mechanics
- Heat transfer
- Incompressible fluid dynamics
- Compressible fluid dynamics
- Electromagnetics
- Particle methods



# Introduction

## Overview

- ALE Fundamentals
- ALE in LS-DYNA
- Lagrangean-Structure Interaction
- Moving Reference Frame
- Output
- Structured ALE (S-ALE)
- Summary

# ALE Fundamentals

---

Under the hood


# ALE Fundamentals

## Overcoming Element Degradation



### Problem

- Large deformations/distortions
- Element performance degradation



### Solution

- Mesh-adaptivity (re-meshing)
- ALE approach




# ALE Fundamentals

Lagrangean vs ALE formulation


## Lagrangeian Formulation

- Nodes are tied to material
- Mesh deforms with the material
- Not suitable for very large deformations, e. g. forging, extrusion, material flow



## ALE formulation

- Nodes are not tied to material
- Nodes are repositioned to avoid excessive mesh distortion
- Relative motion between material and mesh



# ALE Fundamentals

Solving complex PDE



- Numerical methods to solve partial differential equations (PDE), e. g.
  - **Mass balance**
  - **Momentum balance**
  - **Energy balance**
- Numerical solution procedure comprises
  - **Space discretization**, e. g. Finite-Element Analysis (FEA), Smoothed Particle Hydrodynamics (SPH)
  - **Time discretization**, e. g. Backward Euler (BE), Central Difference (CD) scheme

## ALE (Arbitrary Lagrangean Eulerian)

- Is neither one of these
- In particular, it still **exploits FEA and CD for space and time discretization**, respectively
- However, tweaks the update of the solutions state **using Lagrangean and Eulerian formulation**

# ALE Fundamentals

Application examples




# ALE Fundamentals

## Lagrangean vs Eulerian Formulation


### Lagrangean

- Material description
- Follows material motion and observes changes in variable



### Eulerian


- Spatial description
- Observation of material-point attached variables pass by a fixed point




# ALE Fundamentals

## Lagrangean vs Eulerian Formulation vs ALE


Lagrange



Euler



ALE



$t=t_1$

Translation

Deformation

Euler-mesh fixed in space


Moving ALE-mesh

$t=t_2$

 = Advection


# ALE Fundamentals

## ALE time advancement




### FEA Step

- Lagrangean



### Intermediate ALE Steps

- Mesh smoothing
- Advection



- Lagrangean
  - **Mesh distortion** via node movement following material motion, i. e. regular FEA step
- Intermediate ALE Steps
  - **Mesh smoothing**, e. g. average method, equipotential [ Winslow 1963, 1990 ]
  - **Advection**, i. e. material flow, via, e. g., Doner cell, van Leer
- Time step size
  - **CFL stability condition** applies, i. e.


$$\Delta t_{cr} \approx \min_{nel} \left[ \frac{\Delta x^e}{c}, \frac{2\Delta x^e}{v^e} \right]$$

# ALE Fundamentals


## Single vs multi-material ALE

- ALE domain may contain
  - Single material in a vacuum, where only one material obeys a material law → **Single-Material ALE**
  - Several materials, where each material follows its own material law → **Multi-Material ALE**

### Single-Material ALE



### Multi-Material ALE



Use Single-Material ALE only when fluid-fluid interaction is not of concern

# ALE in LS-DYNA

---

## Important Keywords

# ALE in LS-DYNA

## Overview

- **Global control** via \*CONTROL\_ALE, e. g.
  - Advection scheme and advection frequency
  - Reference pressure on ALE domain boundaries
- **Multi-Material Euler/ALE** via \*ALE\_MULTI-MATERIAL\_..., e. g.
  - Multi-Material definitions
  - Initial material distribution
- Material laws via \*MAT\_, \*MAT\_ALE\_, \*EOS\_
- **Lagrangean-structure interaction** via \*CONSTRAINED\_LAGRANGE\_IN\_SOLID
- For **boundary conditions**, mostly the usual \*BOUNDARY\_ keywords apply
- Post-processing via \*DATABASE\_FSI\_...

# ALE in LS-DYNA


## Element formulations

- ELFORM in \*SECTION\_SOLID defines the ALE/Eulerian formulation

```
*PART
$      PID      SECID      MID      EOSID      HGID
          1          1          1


*SECTION_SOLID
$      SECID      ELFORM
          1          11

*MAT_NULL
$      MID      RO      PC      MU      TEROD      CEROD      YM      PR
          1          ...
```



Eulerian ELFORM

ELFORM	EQ. 5: 1 point integration ALE (single material) EQ. 6: 1 point integration Eulerian (single material) ... EQ.11: 1 point integration ALE (multi-material ALE) EQ.12: 1 point integration ALE (single-material ALE and void)
--------	--



ALE ELFORM

# ALE in LS-DYNA

## Multi-Material Definition

- ELFORM in \*SECTION\_SOLID defines the ALE/Eulerian formulation

```
*PART
$      PID      SECID      MID      EOSID      HGID
        1          1          1

*SECTION_SOLID
$      SECID      ELFORM
        1          11

*MAT_NULL
$      MID      RO      PC      MU      TEROD      CEROD      YM      PR
        1          ...
```

ELFORM	EQ. 5: 1 point integration ALE (single material) EQ. 6: 1 point integration Eulerian (single material)
	... <b>EQ.11: 1 point integration ALE (multi-material ALE)</b> EQ.12: 1 point integration ALE (single-material ALE and void)

# ALE in LS-DYNA

## Multi-Material Definition

- Multi-Material Euler/ALE via \*ALE\_MULTI-MATERIAL\_...

```
*ALE_MULTI-MATERIAL_GROUP
$      sid    idtype
      11      1      Multi-material group 1
      22      1      Multi-material group 2
      33      1      Multi-material group 3
      55      1      Multi-material group 4
      ...    ...
```

SID              part or part-set id  
IDTYPE          entity type in SID, i. e. part set, part

### Remarks

- Note that the **multi-material ID are assigned automatically sequentially from top to bottom**
- Only materials of same material group can join or mix, respectively


# Lagrangean-Structure Interaction

Interaction between ALE and FE

# Lagrangean-Structure Interaction

## Basic concepts

- Different problems require different simulation strategies
- Finite-Element Analysis (FEA)
  - **Highly efficient**
  - However, element-distortion-capability limits material deformation
- Arbitrary Lagrangean Eulerian (ALE)
  - **Large deformation and material mixing** possible
  - Less efficient



## FEA-ALE interaction


- FEA for mildly deforming structures, e. g. solid structures
- ALE for heavily distorting materials, e. g. pastes, liquids

# Lagrangean-Structure Interaction

## Methodology


### Constraint-based Method

- ALE-Material velocities are computed at coupling point of Lagrangean structure
- Both velocities are forced to be the same



### Penalty-based Method

- Penalty method punishes violation of constraint via a penalty force
- Penalty force is proportional to amount of violation, e. g. penetration depth



### Remarks

- Interaction activated via \*CONSTAINED\_LAGRANGE\_IN\_SOLID
- For ALE-rigid-body interaction, penalty method, CTYPE=4 in \*CONSTAINED\_LAGRANGE\_IN\_SOLID is needed

# Lagrangean-Structure Interaction

## Keyword

### \*CONSTRAINED\_LAGRANGE\_IN\_SOLID

\$	SLAVE	MASTER	SSTYP	MSTYP	NQUAD	CTYPE	DIREC	MCOUP
	401	402	0	0	1	6	1	-998
\$	START	END	PFAC	FRIC	FRMIN	NORM	NORMTYP	DAMP
	0	0	-999	0	0.2	0		
\$	CQ	HMIN	HMAX	ILEAK	PLEAK	LCIDPORO	NVENT	IBLOCK
	0	0	0	2	0.1			

SLAVE

Slave ID references the **Lagrangean structure**

MASTER

Master ID references the **ALE mesh**

SSTYP

Slave set type, e. g. part set, part or segment

MSTYP

Master set type, e. g. part set or part

NQUAD

Number n of quadrature points to **control leakage**

CTYPE

**Coupling method**, e. g. penalty (CTYPE=4)

...

MCOUP

Multi-material coupling

PFAC

Penalty-stiffness scaling factor if GT.0

...


ILEAK

Leakage-control method


# Lagrangean-Structure Interaction

## Leakage


- Leakage occurs if there are too few coupling points



Too few coupling points (NQUAD=1) → leakage



Sufficient coupling points (NQUAD=4) → leakage



At least, three coupling points on lagrangean-structure segment in ALE is recommended

# Moving Reference Frame

---

# Moving Reference Frame

Rotation and translation of the ALE domain

- To reduce the size number of elements, a moving/transforming ALE mesh can be introduced used via \*ALE\_REFERENCE\_SYSTEM\_GROUP


## \*ALE\_REFERENCE\_SYSTEM\_GROUP

\$	SID	STYPE	PRTYPE	PRID	BCTRAN	BCEXP	BCROT	ICOORD
	2	1	1					1.0
\$	XC	YC	ZC	EXPLIM	EFAC			
	0.0	0.0	0.0	2.0	0.5			

...

**PRTYPE**

reference system type, e. g.  
following coordinate system,  
average velocity of ALE



**BCTRAN**

translational constraints


**BCROT**

rotational constraints

**BCEXP**

mesh-expansion/shrinkage constraint

...




# Outputs

# Outputs

Visualisation data

## ALE group in LS-PrePost

- Go to Model → SelPart
- In the window, tick the check box Fluid(ALE)
- Select the desired ALE groups



## Further Databases

- \*DATABASE\_ALE to select output order of history variables in curve plots and in d3plot
- For specific FSI-related output variables, \*DATABASE\_FSI\_... can be used, e. g.
  - Sensor with offset to Lagrangean surface
- For FSI-pressure fringe plots, use keyword \*DATABASE\_BINARY\_FSIFOR

## Hint

In \*DATABASE\_EXTENT\_BINARY use NEIPH to output integration-point data of ALE history variables


# Structured ALE (S-ALE)

Optimization ALE

# Structured ALE (S-ALE)

## Introduction

- Same theory as „old“ ALE, e. g.
  - Mesh smoothing
  - Advection
  - Lagrangean-structure coupling
- Different implementation
  - **Automatic mesh generation**
  - More **efficient solver**
  - More stable and user-friendly
- S-ALE features
  - Smaller input decks
  - Easier ALE-mesh modifications
  - Enhanced MPP efficiency



ALE (R12.1, MPP, 4 CPU): 89 min.  
S-ALE (R12.1, MPP, 4 CPU): 61 min.  
→ **32 % performance enhancement**

# Structured ALE (S-ALE)

## Keyword Overview

- New class of keywords \*ALE\_STRUCTURED\_
- Mesh generation via
  - \*ALE\_STRUCTURED\_MESH\_CONTROL\_POINTS **a mesh seed** along global coordinates or following a local coordinate system, see \*DEFINE\_COORDINATE\_NODES
  - \*ALE\_STRUCTURED\_MESH **to create the mesh**
- Define materials
  - \*ALE\_MULTI-MATERIAL\_GROUP **to define multi-material groups**
  - \*INITIAL\_VOLUME\_FRACTION\_GEOMETRY **to occupy the newly created structured ALE mesh with material**

## Hints

- Use \*ALE\_STRUCTURED\_MESH\_TRIM to further tailor mesh to match your needs
- Convert existing „old“ ALE mesh to structured mesh, via CPIDX=-1 in \*ALE\_STRUCTURED\_MESH

# Summary

---

Wrap it all up


# Summary

Wrap things up

- **ALE** exploits existing space and time discretization schemes with a twist in the time advancement
  - **Perform Lagrangean step** leading to mesh distortion
  - **Smooth deformed mesh** via mesh motion
  - **Perform advection** (material flow to counter act mesh movement)
- **Explicit method** and, thus, subjected to CFL stability condition
- Applications
  - **Excessive solid deformations**, e. g. in bulk forming
  - **Flow problems**, excl. turbulence and heat transport
- **S-ALE** (enhanced ALE solver)
  - Convenient mesh construction and adaption
  - Usually, **better performance**
  - However, less versatile for complex ALE-domain geometries

# Thank You

---



DYNAmore GmbH  
Industriestr. 2  
70565 Stuttgart-Vaihingen  
Germany

Tel.: +49 - (0)711 - 459 600 0  
Fax: +49 - (0)711 - 459 600 29  
[info@dynamore.de](mailto:info@dynamore.de)

[www.dynamore.de](http://www.dynamore.de)  
[www.dynaexamples.com](http://www.dynaexamples.com)  
[www.dynasupport.com](http://www.dynasupport.com)  
[www.dynalook.com](http://www.dynalook.com)

© 2022 DYNAmore GmbH. All rights reserved.  
Reproduction, distribution, publication or display of the slides and content  
without prior written permission of the DYNAmore GmbH is strictly prohibited.

Find us on



DYNAmore worldwide  
Germany ■ France ■ Italy ■ Sweden ■ Switzerland ■ USA